

MD-5500

MD-5500P


Driver Installation Guide
for Windows 95/98/Me,
Windows 2000,
Windows XP,
and Windows Vista 32

- 1. Windows 95/98/Me 3
 - 1.1. Installing a Printer Attached to a Parallel Port..... 3
 - 1.2. Installing a Printer Attached to a USB Port 5
- 2. Windows XP 9
 - 2.1. Installing Printer Attached to a Parallel Port 9
 - 2.2. Installing a Printer attached to a USB port..... 11
- 3. Vista 32 14
 - 3.1. Installing an Printer attached to a USB port..... 14


1. Windows 95/98/Me

1.1. Installing a Printer Attached to a Parallel Port


- 1.1.1. Do not plug in or power on the printer until the drivers have been loaded
- 1.1.2. Insert the CD-ROM in your CD-ROM or DVD drive
- 1.1.3. Double click setup.exe in the 95-98-Me folder on the CD-ROM
- 1.1.4. Click Yes if you agree to the license conditions




1.1.5. Select your printer and click Next



1.1.6. Select MD_LPT1: and click Next




1.1.7. Click Finish to restart your computer.



1.1.8. Attach the printer to your parallel port and power it on.

1.2. Installing a Printer Attached to a USB Port

- 1.2.1. Insert the driver disk into your CD-ROM or DVD drive
- 1.2.2. Attach the printer to your computer, and power it on
- 1.2.3. The Add New Hardware Wizard starts. Click Next




- 1.2.4. Select Search for the best driver for your device (Recommended) and click Next




- 1.2.5. Uncheck all options except for Specify a location, click Browse, and navigate to the \95-98-ME\USB5500 directory on your CD_ROM or DVD drive. Click Next




- 1.2.6. Click Next




1.2.7. Click Yes if you agree to the license conditions




1.2.8. Select your printer and click Next



1.2.9. Select MD_LPT1: and click Next




1.2.10. Click Finish to restart your computer.




2. Windows XP

2.1. Installing Printer Attached to a Parallel Port


- 2.1.1. Do not plug in or power on the printer until the drivers have been loaded
- 2.1.2. Insert the CD-ROM in your CD-ROM or DVD drive
- 2.1.3. Double click setup.exe in the 2000-XP-Vista32 folder on the CD-ROM
- 2.1.4. Select your printer and click Next



- 2.1.5. Click Yes if you agree to the license conditions. The required files will be copied to your computer. This step can take quite some time depending on the specification of your computer.



2.1.6. Click Finish to complete the setup



2.1.7. Shut down the computer

2.1.8. Plug in the printer


2.1.9. Turn on the computer.

2.1.10. The printer is now ready for use.


2.2. Installing a Printer attached to a USB port

2.2.1. Insert the CD-ROM in your CD-ROM or DVD drive.


2.2.2. Plug the printer in and turn it on The New Hardware Wizard will open. Select “No, not this time” and click Next



2.2.3. Select “Install from a list or specific Location (Advanced)”. Click Next.




- 2.2.4. Select “Search for the best driver in these locations:”. Select “Search removable media (floppy, CD-ROM...)”. Click Next



- 2.2.5. You will be prompted to Stop the installation or continue due to driver signing. Click Continue Anyway



- 2.2.6. Setup will copy the required files. When this process has completed, click Finish




3. Vista 32


3.1. Installing a Printer attached to a USB port

3.1.1. Insert the CD-ROM in your CD-ROM or DVD drive.


3.1.2. Plug the printer in and turn it on The New Hardware Wizard will open. Select “Locate and install driver software (Recommended)”



3.1.3. Vista will ask your permission to continue. Click Continue



- 3.1.4. Vista will find the drivers on the CD-ROM, and warn that the drivers are not signed. Click “Install this driver software anyway”



- 3.1.5. Vista will install the required files. Once the process has completed, click Close

